



Comtarsia Logon Client 2008

Manual

Version: 5.1.14.4, 20 th July, 2011

Contents

1. Introduction.....	3
2. Installation	5
2.1 Automatic Installation	5
3. Comtarsia Management Console (ComtMC)	6
3.1 Update Notification	6
4. Basic Configuraion	7
5. Usage Scenarios	10
5.1 LDAP over SSL.....	10
5.2 LDAP Users from Multiple OUs	12
5.2.1 Search for User.....	12
5.2.2 OU Searchlist.....	14
6. Configuration Parameters	17
6.1 Logon Client.....	17
6.1.1 General	17
6.1.2 Quick Logon.....	19
6.1.3 Scripts	20
6.1.4 User Environment	21
6.1.5 SSO.....	22
6.1.6 User Certificate	23
6.2 LDAP	24
6.2.1 Server.....	24
6.2.2 Users.....	25
Static DN	25
Search for User	26
OU Searchlist	27
6.2.3 User Object	28
6.2.4 Groups	30
6.3 SyncClient.....	32
6.4 Logon	34
6.4.1 Logon Policy	34
6.4.2 Logon Info	36
6.4.3 PKI	37
6.5 Groups	38
6.6 Variables	39
6.7 Logging	42
6.8 Licensing.....	44
7. Comtarsia Logon Client 2006 Comparation.....	45
8. Parameter Description.....	48
9. Scripts for Software Distribution.....	61
9.1 Software Installation	61
9.1.1 install.cmd	61
9.2 Customisation of the (Un-)Installation-Scripts	67
10. Disclaimer.....	70

1. Introduction

Comtarsia Logon Client 2008 for Windows Vista, Windows 7 and Server 2008.



The Comtarsia Logon Client 2008 allows enhances Windows Vista, Server 2008 and Windows 7 with the option of a primary authentication against LDAP-directories.

The Credential Provider interface introduces with Windows Vista and Server 2008 is used by the Comtarsia Logon Client 2008 which replaces the Microsoft Logon tile by a Comtarsia Logon tile which enables the LDAP logon. It's possible to configure the Comtarsia Logon Client 2008 so that users can switch back to the Microsoft Logon tile, or to forbid any other authentication method beside LDAP.



The Windows Vista (and Windows 7) User Account Control (UAC) allows a specific authorisation for the execution of applications which need local Administrator rights. The Comtarsia Logon Client 2008 enables the possibility to use LDAP groups to control these temporary administrator privileges.

For more informations about the Comtarsia SignOn Solutions, please visit our webpage:

http://signon.comtarsia.com/index_en.html

2. Installation

2.1 Automatic Installation

An installation or an update is done using the installation program "SOS2008-5.0.X.4.exe". When updating, the configuration is preserved and the license key will only be replaced if the validity of the installed key is shorter than the validity of the key shipped with the installation program. (Bought license keys usually won't be replaced.)

The installation program copies the necessary files and applies necessary registry changes to enable the Comtarsia Logon Client Credential Provider tile. It also writes a default configuration into the registry (except for those values which have already been set – no existing config will be replaced).

After the installation, the configuration utility „Comtarsia Management Console“ is started. See: [Comtarsia Management Console \(ComtMC\)](#)

3.Comtarsia Management Console (ComtMC)

The Comtarsia Management Console (ComtMC) can be accessed through the Start menu.


On the first start of the ComtMC one will be asked whether "automatic update checking" should be enabled or disabled. If there's no direct internet connection (internet accessible without proxy server), it's advisable to disable automatic update checking for now. This setting can be adjusted at a later time. See:
[Update Notification](#)

3.1 Update Notification

The version checking and notification is performed each time the ComtMC is started.

If there's no direct internet connection (internet accessible without proxy server), it's advisable to disable automatic update checking for now. The update check is carried out exclusively over <http://update.comtarsia.com>

A manual check (Check for update now) can be triggered via the "Update" tab of the ComtMC.



4. Basic Configuration

The configuration of the LDAP settings builds the fundament on which all configuration scenarios build upon.


The following information is needed:

- LDAP-Server Address/Port Non-SSL or SSL
- LDAP server type (eg: OpenLDAP, IBM Directory Server 6, etc)
- LDAP directory structure
- 1 LDAP user with password (for testing)

LDAP directores usually don't follow any rigid pattern and are usually tailored to fit company scenarios and applications. Therefore, the LDAP configuration of the Comtarsia Logon Client often just can not be done by following a simple recipe. This section shows how to obtain a basis configuration which allows an LDAP logon, by following a few simple steps. Additional scenarios which can be used to refine that "simple configuration" follow later together with the required configuration steps. See: [Usage Scenarios](#)

To keep the fundamental configuration simple, it is assumed that all LDAP users are in the same container.

In the hierarchy of the example-LDAP server "ldap.comtarsia.com", the user "mamu1" is in the container "ou=users" which in turn is in "o=comtarsia". "o=comtarsia" is also the BaseDN. The naming-attribute of the example users is "uid". (usually "uid" or "cn")
The full DN (Distinguished Name) of the user is therefore:
"uid=mamu1,ou=users,o=comtarsia".



The syntax of full DNs is always from the lower level (leaf) to the base object (root or "baseDN").


LDAP servers can usually accessed unencrypted over the port 389, as well as SSL-encrypted over the port 636. For the first tests, with the test users, an unencrypted (clear text) communication is sufficient. In production environment, however, an encrypted communication is for security reasons strongly recommended; because otherwise, any communication between the client and the LDAP server (including login information) is held in clear text.

The first configuration to be made is in the Comtarsia Management Console (ComtMC) in the tab "[LDAP] -> [Server]"; The LDAP host name (or IP-address), the LDAP port and the corresponding SSL mode.

If the LDAP communication should be encrypted (over SSL), it's best to chose "SSL without trusted server certificate" instead of "No SSL" for now, for the sake

of simplicity. For more information concerning the SSL modes, see: [LDAP over SSL](#)

Also important is the "BaseDN" which is the base of every LDAP-search.



The tab "[LDAP] -> [Users]" contains the configuration of the position of LDAP-users within the LDAP directory, or "how the authentication" should be performed.

The simplest "UserDN Mode" is "Static DN". In this mode, the Comtarsia Logon Client uses logon name entered by the user (at the logon tile) and uses it to construct an LDAP DN with that name and the configured "BaseDN, UserDN Suffix, and UserDN Prefix". Subsequently, the Comtarsia Logon Client uses that constructed LDAP DN and the password for an LDAP-bind to the configured LDAP server. If the LDAP server accepts that LDAP-bind with the constructed LDAP DN and password, the provided username is considered valid and the logon process continues.

The UserDN is constructed in the following way:

UserDN Prefix + <Logon-Name> + UserDN Suffix + Base DN

The assembly of those parts must result in a valid LDAP DN.


In the example, this results in:

UserDN Prefix=„uid=“

UserDN Suffix=„,ou=Users“ (inclusive the comma)

BaseDN=„o=Comtarsia“

The Comtarsia Management Console shows a preview of the resulting UserDN, so that one can see at a glance whether the chosen values are entered correctly and meet the existing LDAP structure. (marked red in the picture below)



5. Usage Scenarios


5.1 LDAP over SSL

There are different modes of communication between the Comtarsia Logon Client 2008 and the LDAP server.

The basic idea of the SSL communication is the encryption of the plaintext data which is sent over the wire. (1st mode).

The 1st mode is the easiest to configure.

The settings are made in the ComtMC in [LDAP -> Server -> SSL mode].



Description of the modes:

Mode 1: SSL without "trusted server certificate"

Requirements:

Client: none

LDAP Server: SSL communication (ldaps) has to be enabled. The certificate doesn't have to be issued by a CA (Certificate Authority) – it may as well be a self-signed certificate.

Advantages: The communication between the Comtarsia Logon Client 2008 and the LDAP server, (which will otherwise be in clear text) will be encrypted.

Mode 2: SSL with "trusted server certificate"

Requirements:

Client: The client has to trust the CA (Certificate Authority) which issued the LDAP server certificate. Therefore, all CA-certificates in the chain have

to be added to the "Trusted Root Authorities"-branch of the computer-certificates-store. (see figure below)

LDAP Server: The certificate of the LDAP server has to be issued by a certificate authority which is trusted by the client.

Advantages: Encryption. The Comtarsia Logon Client ensures that the LDAP server is trusted by checking its certificate. (prevents "man in the middle"-attacks)


Mode 3: SSL with "trusted client certificate"

Requirements:


Client: As mode 2. In addition, the client needs a client certificate (inclusive key) in the "My"-branch of the computer certificates store. The certificate of each client has to have the computer name its client as part of the certificate CN (common name). (see figure below)

LDAP Server: As mode 2. In addition, the LDAP server has to trust the certificate authority which issued the client certificate.

Advantages: Like mode 2. The LDAP server can be configured to only accept connections from trusted clients.



[Figure: MMC: Trusted Root Certificates of the computer]



[Figure: MMC: My-store of the computer]

5.2 LDAP Users from Multiple OUs


Often, the LDAP hierarchy isn't flat and the users are located in several organizational units (OU).

In the bases (example) configuration, all users are in the OU "ou=Users", which, in turn is within the organisation "o=Comtarsia". However, the following examples have an additional hierarchical level to show the configuration steps required to handle that "multiple Ous"-scenario.

uid=<Username>,ou=<variable OU>,ou=Users,o=Comtarsia

eg:

uid=<Username>,ou=Human Resources,ou=Users,o=Comtarsia
uid=<Username>,ou=Public Relations,ou=Users,o=Comtarsia




[Figure: LDAP example: multiple ou's]

There are different ways to configure this (and similar) scenarios for the Comtarsia Logon Client 2008. The first option ([Search for User](#)), simply searches for the LDAP user within the configured RootDN (on a sub-tree level). The second option ([OU Searchlist](#)) uses a list of allowed OUs, and the Comtarsia Logon Client 2008 searches in each of those OUs for the provided LDAP-user.

In both cases, the LDAP-search either has to be allowed for "anonymous", or a "LDAP system user" has to be used who has the rights to search within the desired parts of the LDAP directory. This system user can be set in the ComtMC and will be used by the Comtarsia Logon Client for those search operations.

5.2.1 Search for User


The Comtarsia Logon Client authenticates itself against the LDAP server, using the configured "System User".



[Figure: ComtMC: LDAP > Users: UserDN Mode = Search for User]

Then, the Logon Client issues an LDAP search, which is composed as follows.:

- (&(uid=<USERNAME>)(objectclass=person)) baseDN: o=Comtarsia
- "<USERNAME>": The username entered by the user.
- "uid)": the configured "UserDN Prefix"
- "person": the configured "User Object > Object Class" (see figure)
- "o=Comtarsia" the configured "baseDN"




[Figure: ComtMC: LDAP > User Object > Object Class]

If an unique LDAP userobject is found, the full DN of this object is used for the LDAP bind request, together with the password provided by the user. In all further steps (eg: group search), this determined LDAP-user DN is used. If the user is not unique (more than one LDAP objects got returned by that LDAP-search), the logon process will be terminated with an error message.

5.2.2 OU Searchlist

The Comtarsia Logon Client authenticates itself against the LDAP server, using the configured "System User".

After that, the Comtarsia Logon Client requests the configured "OU Searchlist > ObjectDN" and its "OU Searchlist > Attribute". This object contains a list of valid "<OU>" -values in the configured "OU Searchlist > Attribute".



[Figure: ComtMC: LDAP > Users > UserDN Mode = OU Searchlist mode]

The configured OU Searchlist Object could be an LDAP group (default configuration); but it can as well be any other LDAP object. By default the "Member"-attribute of a specific LDAP group would contain all the allowed "OUs".

Example LDIF of the OU Searchlist object:

```
dn: cn=ousearchlist, ou=Groups, o=Comtarsia
objectclass: top
objectclass: groupOfNames
member: ou=Accounting
member: ou=Finance
member: ou=Human Resources
member: ou=Information Technology
member: ou=Payroll
member: ou=Public Relations
cn=ousearchlist
```

The Comtarsia Logon Client uses the following values to generate possible valid User-DNs:

<UserDN Prefix><USERNAME><UserDN Suffix><UserOU Prefix><OU><UserOU Suffix>,<basedDN>

In the example configuration, this results in:
uid=<USERNAME>,<jeweilige OU>,o=Comtarsia

- "<UserDN Prefix>": configured in "LDAP > Users > User > UserDN Prefix"
- "<USERNAME>": entered by the user at the login screen
- "<UserDN Suffix>": configured in "LDAP > Users > User > UserDN Suffix"
- "<UserOU Prefix>": configured in "LDAP > Users > OU Seachlist > UserOU Prefix"
- "<OU>": replaced by the respective OUs

- "<UserOU Suffix>": configured in "LDAP > Users > OU Searchlist > UserOU Suffix"
- "<baseDN>": configured in "LDAP > Server > baseDN"

The Comtarsia Logon Client checks each of the resulting DN to see if any of them is a valid LDAP user.


Once a user has been found, the full DN of that user is used, together with the password provided by the user, to issue an LDAP bind. If the LDAP bind succeeds, the logon process continues and the full DN of this user is used for all further steps (eg: group search).

If none of the resulting user-DNs is a valid user, the logon process will be cancelled and the user receives the configured "error code" (LDAP > Users > OU Searchlist > Error Code).

6.Configuration Parameters

6.1 Logon Client

6.1.1 General



Language

Defines the user interface language. Currently the following languages are available: German, English, and French.

Authentication mode

enableSmartcard: Allows to chose between "user password" logon or "pki" (smartcard) logon.

enableProxyLogon: "Direct": the user is authenticated (directly) against the LDAP server. "Proxy": the user credentials (user/password or PKI handshake) is taking place over the Comtarsia SignOn Proxy server which handles the authentication via an LDAP server.

Windows user account

This option activates/deactivates [Enable Domain Logon](#). When set to "Local", the "Local User Mode" is active; "Joined domain" activates the "Domain User Mode".

Local User Mode:

After a successful LDAP logon a local user account is used for the workstation logon. The user account management (create, activation, password synchronization, etc..) is performed by the Comtarsia Logon Client.

Domain User Mode:

After a successful LDAP logon a domain user account is used for the workstation logon. In order for the automatic domain logon to work, two conditions have to be met:

- The workstation has to be a member of the domain
- Since the Comtarsia Logon Client doesn't have the necessary privileges to manage AD-users, the Comtarsia SignOn Gate has to be used on one of the AD servers, and the Comtarsia Logon Client has to be configured to use it. See: [SyncClient Configuration](#).

Microsoft Credential Provider – Filter:

The Comtarsia Logon Client allows you to filter out the standard Microsoft Credential Provider. I.e. Users can't switch to the Microsoft Credential Provider at the logon- or unlock-screen. The Button "other user" is no longer available.

Unregister on Startup

If this parameter is enabled, the Microsoft Credential Provider won't be loaded during the system start. (Comtarsia Credential Provider will be shown as default, but unless "[Disallow temporary activation/deactivation](#)" is also enabled, users can still switch to the Microsoft Credential Provider)

Disallow temporary activation/deactivation

If this option is active, the link "Enable/Disable Microsoft Logon" (at the login screen) is no longer available.

Display progress info bar

If this parameter is activated, a progressbar is displayed on top of the screen during the logon.


LDAP Logon is in progress...

Logon Panel Bitmap

With this parameter, an alternate bitmap (for example a company logo) can be chosen which replaces the Comtarsia logo in the Logon tile.

The bitmap has to have a resolution of 128x128 pixel and has to be locally available to the system during the logon.

6.1.2 Quick Logon



[Enable Quick Logon](#)

Activates a "Quick Logon" button on the logon screen which allows users to log on with predefined credentials (1-click logon)

[Button caption](#)

Specifies the text of the quick-logon button.

[User name](#)

Defines the username which has to be used for the quick logon.


[Password](#)

Defines the password which has to be used for the quick logon.

[Domain](#)

Specifies the quick logon domain. To use an existing local user, this value has to be set to "local" or "%computername%"; otherwise an LDAP logon is performed with the predefined user credentials.

6.1.3 Scripts



The [Timeout](#) parameter specifies the time in seconds within which the scripts have to complete before the Comtarsia Logon Client terminates them.


The [System Init Script](#) is run in the system context at the system startup.

The [System Logon Script](#) is run with system privileges in the system context at each logon.

The [User Logon Script](#) is run with user privileges in the user context at each logon.

If the parameter [No Logon/Logoff scripts for cached cred. Sessions](#) is enabled, the "logon scripts" will be inactive during an offline-/cached credentials logon.

6.1.4 User Environment



The parameter [Profile Path](#) specifies the path to the user profile which has to be assigned to local users.

The parameter [HomeDir Path](#) specifies which path should be assigned as local user's as the "home dir path".

The parameter [HomeDir Drive](#) defines which drive letter should be assigned as the local user's "home dir drive".


In "Domain user mode" (activated [Enable Domain Logon](#)), the Comtarsia Logon Client is unable to assign these values to the domain users (due to privileges). Instead, the Comtarsia SignOn Gate (Agent Configuration) has to handle the user paths.

The default profile path can be assigned via the following value in the Windows System Registry:

HKLM\Software\Microsoft\Windows NT\CurrentVersion\ProfileList\Default

Useful tips about customizing default user profiles and mandatory user profiles under Windows Vista, Windows 7 and Windows Server 2008 can be found in this Microsoft article: <http://support.microsoft.com/kb/973289/de>

6.1.5 SSO



Enable SSO

Enables the Comtarsia Managed Single SignOn (ComtMSSO) module. (this module has to be installed separately)

Root Path

Defines the path to the root directory of the ComtMSSO installation.

Start Modes for Logon Types

Specifies the desired start mode for the Comtarsia Single SignOn module dependant on the logon mode.


Start Modes:

- Don't start SSO: The ComtMSSO module won't be loaded
- Start SSO inactive: The ComtMSSO module will be loaded, but is set "inactive". (The user can enable it via the tray icon, when needed)
- Start SSO active: The ComtMSSO module will be loaded normally.

Logon Types: (via the Comtarsia logon tile)

- [LDAP PWD](#): LDAP-logon via user-password authentication
- [LDAP PKI](#): LDAP-logon via smartcard/token authentication
- [Offline](#): offline logon
- [Local](#): local logon
- [Win ADS](#): active directory logon

6.1.6 User Certificate



This tab is only available in PKI Mode. (see: [Logon Client - General - Authentication mode](#))

A [User Certificate Mapping](#) specifies a regular expression to map the Certificate DN (subject) of the user to an LDAP user dn.

Several User Certificate Mappings can be defined which will be tried in order (top to bottom). The first matching [expression](#) will be used by the Logon Client to determine the LDAP user DN.

The [Mapping name](#) can be any name as it only serves organisational purposes.

The parameter [Expression](#) specifies the regular expression. If the certificates DN (subject) matches with this expression, the [Formatter](#) will be used to determine the resulting LDAP User. (The resulting string will be used to determine the LDAP User)

The parameter [Formatter](#) defines how to map the matching regular expression.

Example:

[Expression:](#) ^[Cc][Nn]=([^,]*),.*

[Formatter:](#) uid=\$1,ou=users,dc=company,dc=com

Certificate DN: cn=mustermann, ou=example, cn=controlling

Resulting LDAP DN: uid=musterman,ou=users,dc=company,dc=com


Certificate DN: cn=mustermann2, dc=company

Resulting LDAP DN: uid=musterman2,ou=users,dc=company,dc=com

6.2 LDAP

6.2.1 Server

LDAP server specific configuration.



LDAP host

Specifies the primary LDAP server.

Failover LDAP host

Specifies a failover LDAP server. This host will only be contacted if the first LDAP server couldn't be reached.

SSL mode

This parameter specifies if, and which SSL mode should be used for the LDAP communication. (See: [LDAP over SSL](#))

LDAP port

The port of the LDAP servers. (default: 389). If another SSL mode is used, the port has to be changed to that LDAP-SSL port. (default for SSL-communication: 636)

Server type

Defines which LDAP server software is in use. This is necessary so that the Comtarsia Logon Client is able to evaluate server specific responses properly (eg: LDAP password policy controls).

Base DN

Specifies the baseDN of all LDAP-operations.


LDAP timeout

Specifies the timeout within which the LDAP-communication has to be finished; otherwise the logon process will be cancelled.

6.2.2 Users

The configuration of "how to determine the LDAP user".

Static DN



Append BaseDN

If this parameter is enabled, the BaseDN is appended to the UserDN. (Default and recommended)

UserDN Prefix

Defines the naming attribute of the LDAP user. The specified value is used for the "Bind as User" operation (static DN), as well as for the LDAP user search (if enabled).

UserDN Suffix

This suffix is appended to the user name for the "Bind as User" (static DN) operation.


UserDN Mode ([searchForUser](#), [ouSearchListMode](#))

Defines how the Logon Client should determine the LDAP DN of the LDAP user object. „Static DN“ defines that the UserDN should be constructed from the

specified values, and that this resulting userDN should be used directly for the LDAP bind operation. (Also see: [LDAP Users from Multiple OUs](#))

DN: Shows the resulting userDN which will be used for the LDAP bind; or, in case of a different "UserDN Mode", the resulting LDAP search string.

Search for User




[System User > DN](#)

Defines a full LDAP DN of a dedicated LDAP system user which will be used for the LDAP search operation (Both for "UserDN Mode: Search for User", and "UserDN Mode: OU Searchlist"). UserDN Modes, other than "static DN" are needed to find LDAP users in case they're in different containers/OUs. (Also see: [LDAP Users from Multiple OUs](#), und [Search for User](#))

[System User > Password](#)

Defines the password of the LDAP system user. The password is stored encrypted.

OU Searchlist



OU Searchlist

Also see: [LDAP Users from Multiple OUs](#), und [OU Searchlist](#)

OU Searchlist > ObjectDN

Specifies which LDAP object contains the list of OUs ([OU Searchlist](#)).

OU Searchlist > Attribute

Specifies which LDAP attribute of that OU Searchlist LDAP object contains the single OU-values. (multivalue attribute)

OU Searchlist > Error Code

Defines which LDAP error should be returned in case the User wasn't found in any of the OUs.

OU Searchlist > UserOU Prefix


Defines a prefix which will be used to construct the particular user DNs.

The possible UserDNs are constructed in the following way:

<UserDN Prefix><USERNAME><UserDN Suffix><UserOU Prefix><OU><UserOU Suffix>,<basedDN>

(Also see: [LDAP Users from Multiple OUs](#), and [OU Searchlist](#))

6.2.3 User Object



User Object

Object Class

Defines which LDAP ObjectClass has to be used to determine the LDAP-user (for Search For User and OU Searchlist).

UserObject Required

If this option is enabled, a logon will only be allowed if the LDAP-user was actually found in the LDAP directory. This usually isn't necessary, unless the LDAP server allows bind requests of non-existent/wrong users.

Password Attribute

Defines in which LDAP attribute of the LDAP user object the password is stored.

UTF8-password

If this option is enabled, the password will be sent UTF8-encoded during the logon, as well as during password-changes. This also affects the system user password.

Don't send old password on change

If this option is enabled, the old password won't be sent together with the new password during a password change request. (Default: old password will be sent. Recommended)

Set Samba Password

The following options can be used to synchronize the LDAP user password with the Samba Password of the LDAP user object. This is useful if the LDAP user objects are also used as samba users.

sambaLMPassword

Updates the LDAP user attribute "sambaLMPassword" with the LM-hash of the user password.

sambaNTPassword

Updates the LDAP user attribute "sambaNTPassword" with the NT-hash of the user password.

sambaPwdLastSet

Updates the LDAP user attribute "sambaPwdLastSet" with the current time stamp (at each logon), to avoid an expiration of the samba password.

Session Password

During a smartcard logon, a session password is generated (dependant on the session password mode), by using the user's private key. The generated session password will be set as Windows user password and if the Sync Client is enabled, it will also be sent to the SignOn Proxy for synchronisation.

set session password

The session password will be written into the configured "password attribute" of the LDAP user object.

Warning: As the users don't know their generated session passwords, they won't be able to authenticate via the LDAP directory via user+password.

password template

This value specifies a template for the generation of the session password.

Following characters can be used:

L	lowercase character (a-z)
U	uppercase character (A-Z)
9	number (0-9)
S	special character (!"#\$%&()'*)+,-./:;<=>?@[\]^_`{ }~)
R	random (randomly one of L, U, 9 or S)

interval mode

This option sets the config "[smartCardSessionPasswordMode](#)" to 1. (interval mode). The interval mode ensures that the generated password stays the same over specified time spans, but also that different workstations generate the same session password. This prevents synchronisation/network-resource access problems if users work on different computers on the network.

validity

Specifies the amount of [validity units](#) a session password remains the same.

validity units


Specifies the unit of the "[validity](#) (amount)".

offset

Specifies an offset in minutes.

For example: A "validity: 1, validity units: days" password always changes at 0:00 each day. Via the offset, this point in time can be changed (in minutes).

6.2.4 Groups



Query Base

With this option, a different base DN can be defined for the group search. By default (if this option is empty), the configured [LDAP > Server > [Base DN](#)] is used.

Query Scope

Specifies the scope of the LDAP group search

- Base: Only the "Query Base" itself.
- One Level: All entries directly within the "Query Base"
- Sub Tree: The whole tree below the "Query Base"

Filter

Specifies an additional LDAP search filter which will be incorporated into the LDAP group search. Groups that do not match this filter will be left out.

With this, it's possible to (examples):

- Check if a specific attribute is existant: (description=*)
- Check if an attribute starts with/ends with/contains a value: (description=Logon*)
- Check if an attribute has a specific value: (GroupUsage=LogonGroup)
- Check if one of several, or several group-requirements are met: (|(GroupUsage=LogonGroup)(GroupUsage=WinGroup))

Group Types

Specifies which types of groups the Comtarsia Logon Client has to look for. This configuration depends on the group types actually used on the LDAP server.

- GroupOfNames


- GroupOfUniqueNames
- PosixGroup
- ibm-AllGroups: a special LDAP user attribute, which only exists on IBM-Directory servers. (ignores [Query Base](#) and [Filter](#))
- memberOf: a special LDAP user attribute, which only exists on Microsoft Active Directory servers (ignores [Query Base](#) and [Filter](#))

[Attribute based groups](#)

With "attribute based groups", it's possible to use attributes of the LDAP user object as if they were groups.

For example, the LDAP user objects have an LDAP attribute "department", it is possible to define "department" as "attributes based group" and use the values of the LDAP attribute "department" as an additional group.

6.3 SyncClient



Enable Sync Client

This option enables the Sync Client. After each successful logon, a Sync-User request will be sent to a specified Comtarsia SignOn Proxy.

SignOn Proxy

Primary host

Specifies the IP-address or host name of the primary Comtarsia SignOn Proxy.

Failover host

Specifies the IP-address or host name of a failover Comtarsia SignOn Proxy.

Port

Specifies the IP-port for the communication to the SignOn Proxy. (default: 2003)

Connect Timeout


Specifies a connect-timeout in seconds.

Sync Packet TTL

Specifies a timeout in seconds for the whole synchronization process.

Display Sync Client Box

If this parameter is enabled, the status of the synchronization is displayed on the upper left corner of the logon screen.



TLS

CA File

This option specifies the path to the CA-certificate.

Cert File

This option specifies the path to the user/computer-certificate.

Key File


This option specifies the path to the user/computer private key.

For more information about the Comtarsia Logon Client <-> SignOn Proxy communication, please refer to the manual [Architectural Manual – SSL Certificates](#) Chapter 2.1.

Additional SignOn Request on

If the parameter [CREDUI LDAP Logon](#) is enabled, a Sync-User request will also be sent after every successful CREDUI LDAP logon.

(eg: For a Windows UAC)




If the parameter [Logged on Password change](#) is enabled, a Sync-User request will also be sent after each LDAP-password change during an active logon session.

If the parameter [Workstation Unlock](#) is enabled, a Sync-User request will also be sent each time the workstation is unlocked.

A time span that has to pass after the last Sync-User request before a new Sync-User request is sent, can be configured via [Time span \(min\)](#).

6.4 Logon

6.4.1 Logon Policy



If the parameter [Disable local logon](#) is enabled, the option „LOCAL LOGON“ won't be available on the logon form below the logon tile.

[Display offline logon option](#)

[Offer offline logon if LDAP server unreachable](#)

The parameter [Username case policy](#) specifies whether to force upper- or lower-case letters for the user name, or to allow upper and lower case letters on the logon form.

No Case Policy: Upper- and lowercase is allowed.

Auto Upper Case: All characters will be converted to upper case letters.

Auto Lower Case: All characters will be converted to lower case letters.

If the option [Disallow grace period login](#) is enabled, a password change dialog which will be shown due to a "LDAP logon during the grace login period", can't be cancelled. (The cancel button is disabled)

If the parameter [Don't display last unusername](#) is enabled, the username of the last successful logon won't be shown in the logon form.

If the parameter [Remove user](#) is enabled, the local user and his/her user profile will be removed after logging off from an LDAP-logon session. This only affects users who have been created by the Comtarsia Logon Client during an LDAP-logon (marked with the user description: "SERV_TEMP_USER").

In domain mode (i.e. there are no local users), this option is ignored. However, one may use the following Windows policy to remove local roaming profiles after each logon session:

REG_DWORD:HKLM\Software\Policies\Microsoft\Windows\System>DeleteRoaming Cache = 1

[Disable RDP autologon](#)


Logon Groups

Logon Groups can be used to allow/deny the logon of users, based on their LDAP group membership (LDAP groups, attribute based groups).

The field [Groups](#) contains a comma-separated list of group names.

The parameter [Mode](#) defines whether the membership of one of the Logon Groups is required for a logon, or forbids the logon. If the [Groups](#) list is empty, the Logon Groups functionality is inactive.

(See: [LDAP-groups](#) and parameter [Attribute based groups](#))



Password

The parameter [Min password length](#) specifies the minimum length an LDAP password must have during a password change or an LDAP logon. If the current LDAP password is shorter, the user will be prompted to change it in order to log on.

The parameter [Alphanumerical passwords only](#) can be used to make sure that users can use alphanumeric characters only, in their passwords. (no special characters are allowed)

Cancelling of the password change dialog can be prevented in the following cases:


- [CLCForcePasswordChange attribute](#): if the password dialog is shown due to the set LDAP attribute "CLCForcePasswordChange" of the LDAP user object.
- [LDAP reset](#): if the password dialog is shown due a "must change on reset"-password policy control returned by the LDAP server.
- [LDAP grace periode](#): if the password dialog is shown due to a "grace period login" (returned password policy control by the LDAP server).

It's possible to prevent the password change in the following cases:

- [on logon](#): via the check box "change password" on the logon screen
- [while logged on](#): during a logged-on session. (Ctrl+Alt+Del screen)
- [by LDAP request](#): if the LDAP server requested a password change (eg: via a "warn expire").
- [by LDAP force request](#): if the LDAP attribute "CLCForcePWDchange" is set for the LDAP user, or the LDAP server returned a "must change password" (eg: due to the LDAP password policy "must change on reset").
- [for local logon](#): during a local logon.

If a password change is prevented due to one of the aforementioned policies, the user will receive the message configured in [Message for the user](#). This is useful if it's required that the users change their LDAP passwords over a web interface.


6.4.2 Logon Info




The parameter [Logon Info Text](#) specifies an alternative text users will see if they click on the "Information" link on the logon form. By default (if the text isn't set), a generic text will be displayed. It's suggested to enter support information, like a

phone hotline, users need in case they can't log on (eg: password expired, account locked, etc.)

6.4.3 PKI



6.5 Groups



The parameter [Except groups](#) defines a comma separated list of group names for which no operation should be carried out. (The user won't be added to, nor removed from these groups.)

The parameter [Create groups](#) defines if LDAP groups (or groups resulting from the group mapping), which don't exist locally, should be created automatically.

The parameter [Windows Group Type](#) defines whether local or global groups should be used. "Global groups" can only be used on a windows domain controller. Global groups are domain global whereas local groups exist on the client computer only.

On a client computer (any non-domain controller), this option has to be set to "Local".

If [Equal group-mapping](#) is enabled, the group names won't be altered by the mapping list. Each LDAP Group will be mapped to a system group one-to-one. Otherwise, a manual "group mapping" list can be specified.
(also see: [LDAP-groups](#) and [AttributeBasedGroups](#))

HwAdmin

The HwAdmin functionality allows to specify a list of computers of which a user is Administrator. The list is stored in a specified [HwAdmin Attribute](#) of the LDAP user object. The parameter [HwAdmin Group](#) specifies which LDAP-groups enables the "HwAdmin" functionality for a user.


The parameter [HwAdmin Attribute](#) specifies which LDAP attribute of the LDAP user object contains the list of computer names for which that user is an administrator. If both criterias are met, the user will be added to the local administrators group. (The name of that group has to be specified via the parameter [LocalAdminGroup](#))

Default groups

Every user who successfully authenticated against the LDAP will be member of the dummy group specified in [Everyone](#). This group can also be used in the group mapping list.

The parameter [No groups](#) specifies a dummy group which should be assigned to every sucessfully authenticated user who has no LDAP groups (inclusive [AttributeBasedGroups](#)) This group can also be used in the group mapping list.

6.6 Variables



Variables are placeholders for variable values which can be obtained from different sources and processed and exchanged between the products within the Comtarsia product family. The values can also be exportet to the respective target systems.

Examples for possible sources: LDAP user object; Windows registry, Computer environment variables, internally provided values.

Examples for possibe export targets: Attributes of the Windows user object (ie. comment, home/profile path, full name); user environment.

The variables can be used/modified at two different points in time which are defined by the tabs "[Before Sync](#)" and "[After Sync](#)".

[Before Sync](#): Variables will be accessed before the user synchronisation (thus they can also be sent to the SignOn Proxy/SignOn Agent)

[After Sync](#): Variables will be processed after the user synchronisation Thus values can be sent back by the SignOn Agent/SignOn Proxy and processed.

The variables will also be processed in order (from top to bottom). The up/down arrow buttons can be used to change that order.

The [Variable name](#) specifies the name of the variable. If the value has to be exportet, the name has to match with the name of the target variable and/or the name of the target attribute.

The [Display name](#) specifies the name to be displayed in the variables list (at the left side). This parameter is used by the configuration utility only and is meant to help organising the variables.

Via "[Export Variable to](#)", variables can be exportet to different target systems.

[User object](#): The value of the user obect (with the name of the value) will be set to the value of the variable.

[User environment](#): The variable will be exported into the user environment (Windows environment variable).

With [Hold](#) variables can be disabled temporarily.

Value

The [Source](#) defines the source/data of the variable. This field can contain text as well as other variables (between two '%'). To use '%' as part of the value '%%' has to be used and will be replaced by '%' rather than used as a variable. The "+" button offers a dialog to add easy-to-use variable source templates.

The [MultiValue action](#) defines how to handle multi value variables (variables which represent an array).

Overwrite: A possibly existing value will be overwritten.

Delete: The variable will be deleted.

DeleteValue: The resulting value will be removed from the existing variable (array).

AddValue: The resulting value will be added to the variable (array). (ie. to add a group to the existing list of groups)

[Use regular expression](#) enabled the 'regular expressions' functionality for this variable..

[Expression](#) defines the regular expression which has to be applied to the resolved value (content/data) of the source. If the source also contains variables, these will be replaced before the regular expression is applied.

The [Formatter](#) defines how to build the resulting value by applying the regular expression on the source value.

The [Index](#) can be used to refer to a specific match if a necessarily more ambiguous regular expression results in more than one match. Usually the index is 0 unless it's impossible to make the regular expression specific enough to result in only 1 match.

The [Flags](#) is a bitmask which specifies the operation mode of the regular expression.

Valid Flags:

```
match_default          0,
match_not_bol         0x00000001, /* first is not start of line */
match_not_eol         0x00000002, /* last is not end of line */
match_not_bob         0x00000004, /* first is not start of buffer
*/
match_not_eob         0x00000008, /* last is not end of buffer */
match_not_bow         0x00000010, /* first is not start of word */
match_not_eow         0x00000020, /* last is not end of word */
match_not_dot_newline 0x00000040, /* \n is not matched by '.' */
match_not_dot_null    0x00000080, /* '\0' is not matched by '.' */
match_prev_avail      0x00000100, /* --first is a valid expression
*/
match_init             0x00000200, /* internal use */
match_any              0x00000400, /* don't care what we match */
match_not_null         0x00000800, /* string can't be null */
match_continuous       0x00001000, /* each grep match must continue
*/
                                         /* uninterrupted from the previous
one */
match_partial          0x00002000, /* find partial matches */
match_stop              0x00004000, /* stop after first match (grep)
V3 only */
match_not_initial_null 0x00004000, /* don't match initial null, V4
only */
match_all               0x00008000, /* must find the whole of input
even if match_any is set */
match_perl              0x00010000, /* Use perl matching rules */
match_posix              0x00020000, /* Use POSIX matching rules */
match_nosubs             0x00040000, /* don't trap marked subs */
match_extra              0x00080000, /* include full capture
information for repeated captures */
match_single_line        0x00100000, /* treat text as single line and
ignor any \n's when matching ^ and $. */
match_unused1            0x00200000, /* unused */
match_unused2            0x00400000, /* unused */
match_unused3            0x00800000, /* unused */
match_max                0x00800000,
format_perl              0,           /* perl style replacement */
format_default            0,           /* ditto. */
format_sed                0x01000000, /* sed style replacement. */
format_all                0x02000000, /* enable all extentions to
syntax. */
format_no_copy            0x04000000, /* don't copy non-matching
segments. */
format_first_only          0x08000000, /* Only replace first occurrence.
*/
format_is_if              0x10000000, /* internal use only. */
format_literal             0x20000000, /* treat string as a literal */

```


Transmit Destination

The [Transmit Destination](#) specifies to which other Comtarsia SignOn products this variable should be sent to. (Invalid destinations are greyed out)

If the [Transmit Destination](#) 'SignOn Agent 0x8' is set (only possible on the SignOn Proxy) the option [Domains](#) can be used to specify to which SignOn Agent

domains this variable should be sent. If this field is empty, the variable will be sent to all SignOn Agents.

6.7 Logging



Log File

Enable

Enables/disables writing to the log file.

Loglevel

The LogLevel defines the verbosity of the log written to the specified file. The "detail log flags" are handled independently of the LogLevel.

Eg: It's perfectly valid to use "LogLevel"=None, and "Detail Log Flags"=Monitor to only log "monitoring"-messages.

- None: No logging, except detail log flags.
- Error: Only errors and specified detail log flags.
- Exception: As Error, and exception messages.
- Warn: As Exception, and warnings.
- Info: As Warn, and additional information
- Detail MSG: Everything (except unspecified log flags which have to be enabled separately)

Log filename

Defines the path to the log file.

Max logfile size

Defines the size at which the logfile should be rotated.

Max logfile history

Defines the amount of logfiles to be rotated.


Detail Log Flags

Detail Log Flags enable specific log output independent of the Loglevel.
The Detail Log Flag "Monitor" is recommended for centralized monitoring.

Log Line Details

Defines which details are to be included in each log line.

- Date
- Time
- PID & TID: Process and thread ID.
- Source pos: The position (line) in the source code.



SysLog

Enable

Enables/disables forward of log messages to a syslog server.

LogLevel

The LogLevel defines the verbosity of the log written to the specified file. The "detail log flags" are handled independently of the LogLevel.

E.g.: It's perfectly valid to use "LogLevel"=None, and "Detail Log Flags"=Monitor to only log "monitoring"-messages.

- None: No logging, except detail log flags.
- Error: Only errors and specified detail log flags.
- Exception: As Error, and exception messages.
- Warn: As Exception, and warnings.
- Info: As Warn, and additional information
- Detail MSG: Everything (except unspecified log flags which have to be enabled separately)

Syslog host

Defines the central SysLog host to which the SysLog messages will be sent.

Syslog facility

Specifies the SysLog facility of the log messages.

Detail Log Flags


Detail Log Flags enable specific log output independent of the Loglevel.
The Detail Log Flag "Monitor" is recommended for centralized monitoring.

Log Line Details

Defines which details are to be included in each log line.

- Date
- Time
- PID & TID: Process and thread ID.
- Source pos: The position (line) in the source code.

6.8 Licensing



Displays information about the installed license key. The button "Load another license key" opens a file chooser dialog and copies the specified license key (Filename "key042") to the directory %ProgramFiles%\Comtarsia\SignOn Solutions 2008\Key.

7.Comtarsia Logon Client 2006 Comparation

Colors:

CLC 2006 Configuration
CLC 2008 Configuration

"DisableMsGina"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonClient]
"UnregisterMsCredProvider"=dword:00000001
"DisableMsCredProviderToggle"=dword:00000001

Groupmapping

"GroupAdministrator"="0xWS"
"GroupPowerUser"="0xPU"

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\GroupMapping]
@=""
"0xWS"="Administrators"
"0xPU"="PowerUser"
"0xWS"="Administratoren"
"0xPU"="Hauptbenutzer"

Mode

"EnableDomainLogon"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonClient]
"EnableDomainLogon"=dword:00000001
"WinDomain"="ADSDOM146"

"EnableSyncClient"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonClient]
"EnableSyncClient"=dword:00000001

"DisableLocalLogon"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]
"DisableLocalLogon"=dword:00000000

HomeDir

"HomeDirDrive"="Z:"
"HomeDirPath"="\QA\physicaldeliveryofficename%A01\users\$\%USERNAME%"

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\UserEnvironment]
"HomeDirDrive"="Z"
"HomeDirPath"="\QA\physicaldeliveryofficename%A01\users\$\%USERNAME%"

PWD

"MinPwdLen"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]

"MinPwdLen"=dword:00000001

USER

"UserNameCasePolicy"=dword:00000001

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]
"UserNameCasePolicy"=dword:00000001

LDAP

"LDAPEnableSSL"=dword:00000002

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile
001\LDAP\Servers\lind.comtarsia.com]
"sslMode"=dword:00000002

"EnableLDAP"=dword:00000001

Dieser Parameter ist nicht mehr mehr notwendig

GPUpdate

"GPUpdate_CMD"="gpupdate.cmd"

"GPUpdate_Mask"=dword:00000102

Noch nicht implementiert, (kann derzeit mit Scripts gelöst werden)->

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\Script]

"UserLogon"=" gpupdate.cmd "

"SystemLogon"=" gpupdate.cmd "

SSO:

"EnableSSOExec"=dword:00000002

"MSSORootPath"="C:\\Programme\\Comtarsia\\ComtMSSO"

"EnableSSO"=dword:00000003

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\SSO]

"EnableSSO"=dword:000000000

"RootPath"=""

OUT-Parameter

"USID"="S-1-5-21-1630323187-507556056-2246393201-1296"

"CSID"=

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\temp]

"USID"="S-1-5-21-157906255-4040051303-1972554199-500"

"CSID"= "S-1-5-21-157906255-4040051303-1972554199"

Disabled

"DontDisplayLastUserName"=dword:00000000

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]

"DontDisplayLastUserName"=dword:00000000

"ProfilePath"=""

[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile
001\UserEnvironment]

```
"ProfilePath=""  
"DenyCancleForcePWDChangeDlg"=dword:00000000  
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]  
"DenyCancleForcePWDChangeDlg"=dword:00000001
```

Scripts:

```
"DisplayScriptError"=dword:00000001  
"ScriptTimeout"=dword:000000b4  
"NoScriptsByCachedCredLogon"=dword:00000001  
"UserLogoffScript"="\\\\%INSTSRV%\netlogon\UserLogoff.cmd"  
"UserLogonScript"="\\\\%INSTSRV%\netlogon\UserLogon.cmd"  
"DisableEqualGroupMapping"=dword:00000001
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\Script]  
"Timeout"=dword:000000b4  
"UserLogon""  
"UserLogoff""  
"SystemLogon""  
"SystemLogoff""  
"SystemInit""
```

Groupmapping

```
"HwAdminAttribute"="uniquauapname"  
"HwAdminGroup"="APP-UAP-HWAdmin"
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\Group]  
@=""  
"HwAdminGroup"="localhwadmin"  
"HwAdminAttribute"=""
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\GroupMapping]  
@=""  
"GROUP1"="Administrators"  
"GROUP3"="lg1"
```

WkstLogonPolicy

```
"EnableWkstLogonPolicy"=dword:00000001  
"WkstLogonPolicyRootOUGroups"=hex(7):4f,00,55,00,3d,00,55,00,41, ....
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\LogonPolicy]  
"AlphaNumPwd"=dword:00000000  
"DisablePasswordChange"=dword:00000000  
"DisallowGraceLogin"=dword:00000000
```

```
[HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile 001\Log]  
"logLevel"=dword:00000005  
"logMask"=dword:00001400
```

8.Parameter Description

[HKLM\SOFTWARE\Comtarsia]

[.\SignOn Solutions 2008]

path

path=REG_SZ:"C:\\Program Files\\Comtarsia\\SignOn Solutions 2008"
Product installation directory.

[.\SignOn Solutions 2008\Components]

[.\SignOn Solutions 2008\DefaultProfiles]

LogonClient

LogonClient=REG_SZ:"SOSProfile 001"

[.\SignOn Solutions 2008\LogonClient]

userInit

userInit=REG_SZ:"%SYSTEMROOT%\\system32\\userinit.exe"

credProvMode

credProvMode=REG_DWORD:0

detectedCredProvMode

detectedCredProvMode=REG_DWORD:0

displayCredProvConfig

displayCredProvConfig=REG_DWORD:0

[.\SOSProfile *]

language

language=REG_SZ:"Auto"

Language of the user interface. (Logon screen, messages)

profileName

profileName=REG_SZ:""

profileComment

profileComment=REG_SZ:""

profileConfigVersion

profileConfigVersion=REG_SZ:""

[.\SOSProfile *\Group]

Configuration of the system specific groups.

equalGroupMapping

equalGroupMapping=REG_DWORD:0

0: use the groupmapping list to map LDAP groups to system groups

1: use the LDAP groups 1:1 without mapping

exceptGroups

exceptGroups=REG_SZ:""

A comma seperated list of group names which should be ignored.

globalGroups

globalGroups=REG_DWORD:0

0: use local system groups

1: Use global groups (only valid on domain controllers)

HwAdminGroup

HwAdminGroup=REG_SZ:""

HwAdminAttribute

HwAdminAttribute=REG_SZ:""

HwAdminUSIDRegKey

HwAdminUSIDRegKey=REG_SZ:""

HwAdminSubOU

HwAdminSubOU=REG_SZ:""

localAdminGroup

localAdminGroup=REG_SZ:""

createGroups

createGroups=REG_DWORD:0

Create non-existing groups.

defaultEveryoneGroup

defaultEveryoneGroup=REG_SZ:"#Everyone"

A default group every LDAP user will be a member of. It can also be used with group mapping.

defaultNoGroup

defaultNoGroup=REG_SZ:"#NoGroup"

A default group every LDAP user who doesn't have any LDAP groups will be a member of.

[.\SOSProfile *\GroupMapping]

[.\SOSProfile *\LDAP]

[.\SOSProfile *\LDAP\Servers]

[.\SOSProfile *\LDAP\Servers\<LDAP-Server>]

The name of this key (<LDAP-Server>) is also the hostname of the LDAP server

priority

priority=REG_DWORD:0

failoverHost

failoverHost=REG_SZ:""

baseDN

baseDN=REG_SZ:"o=comtarsia"

The LDAP baseDN

userDNPrefix

userDNPrefix=REG_SZ:"uid=

userDNSuffix

userDNSuffix=REG_SZ:",ou=sd"

userOUPrefix

userOUPrefix=REG_SZ:""

userOUSuffix

userOUSuffix=REG_SZ:""

userObjectClass

userObjectClass=REG_SZ:"Person"

userObjectRequired

userObjectRequired=REG_DWORD:0

userQueryScope

userQueryScope=REG_DWORD:2

groupTypes

groupTypes=REG_DWORD:7

groupQueryBase

groupQueryBase=REG_SZ:""

groupQueryScope

groupQueryScope=REG_DWORD:2

attributeBasedGroups

attributeBasedGroups=REG_MULTI_SZ:"System.String[]"

userPasswordAttribute

userPasswordAttribute=REG_SZ:"userPassword"

timeout
timeout=REG_DWORD:0xA

port
port=REG_DWORD:0x185

sslMode
sslMode=REG_DWORD:0

serverType
serverType=REG_DWORD:0x0

useUTF8Password
useUTF8Password=REG_DWORD:0

dontSendOldPasswordOnChange
dontSendOldPasswordOnChange=REG_DWORD:0

systemUserDN
systemUserDN=REG_SZ:""

systemUserPassword
systemUserPassword=REG_SZ:""

OUSearchListMode
OUSearchListMode=REG_DWORD:0

OUSearchListErrorCode
OUSearchListErrorCode=REG_DWORD:6

OUSearchListObjectDN
OUSearchListObjectDN=REG_SZ:""

OUSearchListAttribute
OUSearchListAttribute=REG_SZ:""

appendBaseDN
appendBaseDN=REG_DWORD:1

searchForUser
searchForUser=REG_DWORD:0

groupFilter
groupFilter=REG_SZ:""

ignoreNoUniqueUser
ignoreNoUniqueUser=REG_DWORD:0

failoverOnUserNotFound
failoverOnUserNotFound=REG_DWORD:0

setSessionPasswordasUserPassword
setSessionPasswordasUserPassword=REG_DWORD:0

followReferrals**followReferrals**=REG_DWORD:1**[.\SOSProfile *\Log]****enable****enable**=REG_DWORD:1

With this parameter, this logging-method can be enabled/disabled.

logFileName**logFileName**=REG_SZ:"%ProgramFiles%\Comtarsia\SignOn Solutions 2008\Log\ComtRPCSrv.log"**logLevel****logLevel**=REG_DWORD:4

Specifies the log level.

URGENCY_ERROR = 1,
URGENCY_EXCEPTION = 2,
URGENCY_WARN = 3,
URGENCY_INFO = 4,
URGENCY_MSG = 5,**logMask****logMask**=REG_DWORD:0**logDetails****logDetails**=REG_DWORD:0xFFFFFFFF

Specifies the log details.

logDetails = 0x0 = No log details
logDetails = 0x1 = Date
logDetails = 0x2 = Time
logDetails = 0x4 = Process and thread ids.
logDetails = 0x8 = Source position
logDetails = 0xFFFFFFFF = All details**enableLogTransactions****enableLogTransactions**=REG_DWORD:0**maxLogFileSize****maxLogFileSize**=REG_DWORD:0xA00000**maxLogFileHistory****maxLogFileHistory**=REG_DWORD:1**[.\SOSProfile *\Log\SysLog]****enable****enable**=REG_DWORD:0

With this parameter, this logging-method can be enabled/disabled.

host

host=REG_SZ:""
Specifies the SysLog server.

facility
facility=REG_DWORD:10
Specifies the SysLog facility.

logLevel
logLevel=REG_DWORD:0
Specifies the log level.
URGENCY_ERROR = 1,
URGENCY_EXCEPTION = 2,
URGENCY_WARN = 3,
URGENCY_INFO = 4,
URGENCY_MSG = 5,

logMask
logMask=REG_DWORD:0

logDetails
logDetails=REG_DWORD:0x0
Specifies the log details.
logDetails = 0x0 = No log details
logDetails = 0x1 = Date
logDetails = 0x2 = Time
logDetails = 0x4 = Process and thread ids.
logDetails = 0x8 = Source position
logDetails = 0xFFFFFFFF = All details

[.\SOSProfile *\SyncClient]

connectTimeout
connectTimeout=REG_DWORD:5

proxyPort
proxyPort=REG_DWORD:0x7D3

syncPacketTTL
syncPacketTTL=REG_DWORD:0x14

syncProxy1
syncProxy1=REG_SZ:""

syncProxy2
syncProxy2=REG_SZ:""

tlsCAFile
tlsCAFile=REG_SZ:"%ProgramFiles%\Comtarsia\SignOn Solutions
2008\cert\ca.pem"

tlsCADir
vn=REG_SZ:""

tlsCertFile

tlsCertFile=REG_SZ:"%ProgramFiles%\Comtarsia\SignOn Solutions 2008\cert\client.pem"

tlsKeyFile

tlsKeyFile=REG_SZ:"%ProgramFiles%\Comtarsia\SignOn Solutions 2008\cert\client.key"

[.\SOSProfile * \UserCertificateMapping]

**[.\SOSProfile * \UserCertificateMapping **

The name of this key (<UserCertificateMappingName>) is in the form NNN_MappingName, where 'N' are numbers and define the order of the mapping rules. The first matching rule will be applied.

expression

expression=REG_SZ:""

formatter

formatter=REG_SZ:""

[.\SOSProfile * \Variables]

[.\SOSProfile * \Variables\BeforeSync]

[.\SOSProfile * \Variables\AfterSync]

[.\SOSProfile

*** \Variables\<VariableEffectivePoint>]**

The name of this key can be "BeforeSync" or "AfterSync" and defines when the variables under this key should be mapped.

[.\SOSProfile

*** \Variables\<VariableEffectivePoint>\<VariableName>]**

The name of this key (<VariableName>) is in the form NNN_Name, where 'N' are numbers and define the order of the mapping rules. The 'Name' is the resulting name of the variable.

displayName

displayName=REG_SZ:""

variableComment

variableComment=REG_SZ:""

source

source=REG_SZ:""

transmitDestination
transmitDestination=REG_DWORD:0x0

exportDestination
exportDestination=REG_DWORD:0x0

transmitDestinationDomains
transmitDestinationDomains=REG_MULTI_SZ:"System.String[]"

mappingType
mappingType=REG_DWORD:0

expression
expression=REG_SZ:""

formatter
formatter=REG_SZ:""

index
index=REG_DWORD:0

flags
flags=REG_DWORD:0x2000000

multivalueAction
multivalueAction=REG_DWORD:0
0:Override
1:Delete
2:DeleteValue
3:AddValue

hold
hold=REG_DWORD:0
This option can be used to temporarily disable a variable mapping.

[.\SOSProfile *\UserEnvironment]

defaultUserProfile
defaultUserProfile=REG_SZ:""

profilePath
profilePath=REG_SZ:""

homeDirDrive
homeDirDrive=REG_SZ:"H:"

homeDirPath
homeDirPath=REG_SZ:""

[.\SOSProfile *\LogonClient]

displayProgressBar

displayProgressBar=REG_DWORD:1

enableSyncClient

enableSyncClient=REG_DWORD:0

displaySyncBox

displaySyncBox=REG_DWORD:1

WTSMode

WTSMode=REG_DWORD:0

ADSLogonMode

ADSLogonMode=REG_DWORD:0

winDomain

winDomain=REG_SZ:""

enableDomainLogon

enableDomainLogon=REG_DWORD:0

userinit

userinit=REG_SZ:"%SYSTEMROOT%\system32\userinit.exe"

GPUpdate_Mask

GPUpdate_Mask=REG_DWORD:0

GPUpdate_CMD

GPUpdate_CMD=REG_SZ:""

disableMsCredProviderToggle

disableMsCredProviderToggle=REG_DWORD:0

unregisterMsCredProvider

unregisterMsCredProvider=REG_DWORD:0

panelBitmap

panelBitmap=REG_SZ:""

refreshUnlockTimer

refreshUnlockTimer=REG_DWORD:720

removeUser

removeUser=REG_DWORD:0

bitmask: (only for local mode)

0x1 User Account

0x2 Profile // (0x1 User Account, 0x2 Profile), only local mode.

LDAPSetPasswordAsSambaPassword

LDAPSetPasswordAsSambaPassword=REG_DWORD:0

enableSmartCard
enableSmartCard=REG_DWORD:0

smartCardDefaultRemoveAction
smartCardDefaultRemoveAction=REG_DWORD:2

smartCardRemoveActionUserSelectMask
smartCardRemoveActionUserSelectMask=REG_DWORD:0xF

logonPanelTileDisplayName
logonPanelTileDisplayName=REG_SZ:""

enableProxyLogon
enableProxyLogon=REG_DWORD:0

sessionPasswordTemplate
sessionPasswordTemplate=REG_SZ:"LLUURR99SS"

smartCardSessionPasswordMode
smartCardSessionPasswordMode=REG_DWORD:0

smartCardSessionPasswordValidity
smartCardSessionPasswordValidity=REG_DWORD:1

smartCardSessionPasswordValidityUnits
smartCardSessionPasswordValidityUnits=REG_DWORD:0

smartCardSessionPasswordValidityOffset
smartCardSessionPasswordValidityOffset=REG_DWORD:0

smartCardSecurePINEntryMode
smartCardSecurePINEntryMode=REG_DWORD:1

displayMsgStrID
displayMsgStrID=REG_DWORD:0

[.\SOSProfile *\LogonPolicy]

minPwdLen
minPwdLen=REG_DWORD:0

alphaNumPwd
alphaNumPwd=REG_DWORD:0

userNameCasePolicy
userNameCasePolicy=REG_DWORD:1

disablePasswordChange
disablePasswordChange=REG_DWORD:0

disableLocalLogon
disableLocalLogon=REG_DWORD:0

changePasswordInfo
changePasswordInfo=REG_SZ:"Password change is disabled!"

denyCancelForcePWDChangeDig
denyCancelForcePWDChangeDig=REG_DWORD:0

disallowGraceLogin
disallowGraceLogin=REG_DWORD:0

dontDisplayLastUserName
dontDisplayLastUserName=REG_DWORD:0

logonAllowGroups
logonAllowGroups=REG_SZ:""

negateLogonAllowGroups
negateLogonAllowGroups=REG_DWORD:1

enableWkstLogonPolicy
enableWkstLogonPolicy=REG_DWORD:0

wkstLogonPolicyRetryTimer
wkstLogonPolicyRetryTimer=REG_DWORD:60

wkstLogonPolicyRootOUGroups
wkstLogonPolicyRootOUGroups=REG_MULTI_SZ:"System.String[]"

logonInformationText
logonInformationText=REG_SZ:""

offerOfflineLogonByUnreachableLDAP
offerOfflineLogonByUnreachableLDAP=REG_DWORD:1

offerOfflineLogonAsLogonOption
offerOfflineLogonAsLogonOption=REG_DWORD:0

enableQuickLogon
enableQuickLogon=REG_DWORD:0

quickLogonButtonCaption
quickLogonButtonCaption=REG_SZ:""

quickLogonUser
quickLogonUser=REG_SZ:""

quickLogonPassword
quickLogonPassword=REG_SZ:""

quickLogonDomain
quickLogonDomain=REG_SZ:""

disableRdpAutoLogon

```
disableRdpAutoLogon=REG_DWORD:0  
setAsDefaultLogonTile  
setAsDefaultLogonTile=REG_DWORD:1
```

[.\SOSProfile *\Script]

```
userLogon  
userLogon=REG_SZ:""  
  
userLogoff  
userLogoff=REG_SZ:""  
  
systemLogon  
systemLogon=REG_SZ:""  
  
systemLogoff  
systemLogoff=REG_SZ:""  
  
systemInit  
systemInit=REG_SZ:""  
  
timeout  
timeout=REG_DWORD:0x1E
```

```
noScriptByCachedCredLogon  
noScriptByCachedCredLogon=REG_DWORD:0
```

[.\SOSProfile *\SSO]

```
rootPath  
rootPath=REG_SZ:"%PROGRAMFILES%\Comtarsia\ComtSSO"  
  
enableSSO  
enableSSO=REG_DWORD:0  
  
LDAP_PWD_MODE  
LDAP_PWD_MODE=REG_DWORD:2  
  
LDAP_PKI_MODE  
LDAP_PKI_MODE=REG_DWORD:2  
  
OFFLINE_MODE  
OFFLINE_MODE=REG_DWORD:2  
  
LOCAL_LOGON_MODE  
LOCAL_LOGON_MODE=REG_DWORD:2  
  
WIN_ADS_MODE  
WIN_ADS_MODE=REG_DWORD:2
```


9. Scripts for Software Distribution

9.1 Software Installation

The following software distribution script performs the following operations:

- .) Unpacking of the "SOS2008-setup-bundle-* .exe" installation package
- .) Determination of the SOS2008 version number
- .) Unpacking of the platform specific files of the LC2008-5.1.*.31.exe package (32/64bit)
- .) Determination of the LC2008 version number
- .) Unpacking of the "MC2008-5.1.*.21.exe" installation package (to retrieve the Comtarsia Management Console)
- .) Stopping of the Comtarsia Services, if installed
- .) Copying of the files to the target directory
- .) Registering of the Credential Provider
- .) Importing of the registry file and ensuring that no pre-existing LDAP servers will be left
- .) SOS2008 and LC2008 version numbers are set in the registry
- .) "ComtMC.exe applyDefault" is started (eventually necessary config conversion will be processed by the Comtarsia Management Console)
- .) UserInit will be set to Comtarsia Userinit (unless set already) and existing UserInit entry will be saved in the Comtarsia registry key
- .) Services are installed if required
- .) Services are started

To use the software distribution script, the following steps have to be performed:

The script must be saved to a local directory, together with the following files:

SOS2008-setup-bundle-* .exe
LC2008.reg
key042

SOS2008-setup-bundle-* .exe

The Comtarsia software installation package to install.

LC2008.reg

The configuration to be imported (exported from a pre-configured reference system: HKEY_LOCAL_MACHINE\Software\Comtarsia)

key042

The customer license key (only if available).

Then the script must be run with administrator privileges.

9.1.1 install.cmd

```
@echo off
:: ######
:: instructions: place this script into a local directory
:: together with:
::   .) SOS2008-setup-bundle-* .exe
::   .) LC2008.reg
::   .) key042 (Customer license key, if available)
:: LC2008.reg has to contain the TESTED Logon Client settings
:: (exportet HKEY_LOCAL_MACHINE\Software\Comtarsia key)
```

```

:: ######
SETLOCAL
:: ##### Configuration
:: regfile has to point to a registry file which contains the desired
configuration.
set regfile=%CD%\LC2008.reg

:: installation directory
set COMT_INSTALL_PATH=C:\Program Files\Comtarsia\SignOn Solutions 2008

:: #####
:: ##### Don't change code below this line #####
:: set "DBE" to echo, to enable debug echo, otherwise set it to ":""
set DBE=echo
:: xcp is used for xcopy and specifies whether it should ask about overwriting
files or not. set to "xcopy /Y" for overwriting without asking
set xcp=xcopy /Y
:: regparam specifies an additional parameter for the "reg" command. set to "/f"
to ommit prompts
set regparam=/f
set cnt=0
set SOSInstallerFile=""
set SOSInstallerDir=""
set SOSVersion=""
set LCInstallerFile=""
set LCInstallerDir=""
set LCVersion=""
set MCInstallerFile=""
set MCInstallerDir=""
set MCInstallerVersion=""

set initialDir=%CD%
set SOSInstallerWildcard=SOS2008-setup-bundle-*.exe
set LCInstallerWildcard=LC2008-5.1.*.31.exe
set MCInstallerWildcard=MC2008-5.1.*.21.exe

:: ## check if reg file exists
IF EXIST "%regfile%" GOTO :regFileExists
set ERRORSTR=Registry File "%regfile%" does not exist. This file is required for
the unattended installation and has to contain the desired configuration.
goto :ERROR
:regFileExists

:: ##### extracting SOS Installer
:: ## get SOSInstallerFile
for %a in ("%SOSInstallerWildcard%") do set SOSInstallerFile=%a&& set /A
cnt=(cnt+1) && echo %a

:: ## check if 1 (and only 1) SOS installer file found
IF NOT "%cnt%"=="0" GOTO :cntSOSNotNull
set ERRORSTR=%SOSInstallerWildcard% not found.
goto :ERROR

:cntSOSNotNull
IF "%cnt%"=="1" GOTO :cntSOSFoundOne
set ERRORSTR=more than one file matching %SOSInstallerWildcard% found (%cnt%)
goto :ERROR

:cntSOSFoundOne

:: ## extract the bundle number and set SOSInstallerDir
set BundleNumber=%SOSInstallerFile:~21,-4%
set SOSVersion=5.1.%BundleNumber%.11

```

```

set SOSInstallerDir=SOS2008-%SOSVersion%

:: ## extracting SOSInstaller and changing to SOSInstallerDir
echo found SOSInstaller: "%SOSInstallerFile%"
echo extracting to "%SOSInstallerDir%" ...
%SOSInstallerFile% /unpack
cd %SOSInstallerDir%


:: ##### extracting LC Installer
:: ## get LCInstallerFile
set cnt=0
for %%a in ("%LCInstallerWildcard%") do set LCInstallerFile=%%a&& set /A
cnt=(cnt+1) && echo %%a

:: ## check if 1 (and only 1) LC installer file found
IF NOT "%cnt%"=="0" GOTO :cntLCNotNull
set ERRORSTR=%LCInstallerWildcard% not found.
goto :ERROR

:cntLCNotNull
IF "%cnt%"=="1" GOTO :cntLCFoundOne
set ERRORSTR=more than one file matching %LCInstallerWildcard% found (%cnt%)
goto :ERROR

:cntLCFoundOne

:: ## extract the LCInstallerDir from LCInstallerFile
set LCVersion=%LCInstallerFile:~7,-4%
set LCInstallerDir=%LCInstallerFile:~0,-4%

echo LCInstallerFile: %LCInstallerFile%
echo LCInstallerDir: %LCInstallerDir%

:: ## Unpack command for LCInstaller depends on Processor architecture
set UNPACKCommand=""
IF "%PROCESSOR_ARCHITECTURE%"=="x86" set UNPACKCommand=/unpack
IF "%PROCESSOR_ARCHITECTURE%"=="AMD64" set UNPACKCommand=/unpack64
IF NOT "%UNPACKCommand%"=="" GOTO :archOK
set ERRORSTR=Unknown processor architecture: %PROCESSOR_ARCHITECTURE% Expected:
x86 or AMD64
goto :ERROR

:archOK
%DBe% using unpack command %UNPACKCommand% for processor architecture
%PROCESSOR_ARCHITECTURE%
:: ## extracting LCInstaller
%LCInstallerFile% %UNPACKCommand%


:: ##### extracting MC Installer (needed for "ComtMC applydefault")
:: ## get MCInstallerFile
set cnt=0
for %%a in ("%MCInstallerWildcard%") do set MCInstallerFile=%%a&& set /A
cnt=(cnt+1) && echo %%a

:: ## check if 1 (and only 1) MC installer file found
IF NOT "%cnt%"=="0" GOTO :cntMCNotNull
set ERRORSTR=%MCInstallerWildcard% not found.
goto :ERROR

:cntMCNotNull
IF "%cnt%"=="1" GOTO :cntMCFoundOne
set ERRORSTR=more than one file matching %MCInstallerWildcard% found (%cnt%)
goto :ERROR

```

```

:cntMCFoundOne

:: ## extract the MCInstallerDir from MCInstallerFile
set MCVersion=%MCInstallerFile:~7,-4%
set MCInstallerDir=%MCInstallerFile:~0,-4%

echo MCInstallerFile: %MCInstallerFile%
echo MCInstallerDir: %MCInstallerDir%

:: ## extracting MCInstaller
%MCInstallerFile% /unpack

:: ##### after extracting MCInstaller
:: changing to LCInstallerDir
cd %LCInstallerDir%

:: #### actual installer

call :stopServices
call :copyFilesToInstallDir
call :registerCredProv
call :applySettingsAndUserInit
call :installAndStartServices

%DBe% done
:: ##### after extracting LC Installer
:: ##### after extracting SOS Installer
GOTO :END

:: ##### Functions #####
GOTO :END

:: #####
:: ##### stop Services so that Files aren't in use:
:stopServices
%DBe% %0
call :stopServiceIfExists ComtEventSrv
call :stopServiceIfExists ComtRPCSrv
goto :eof

:: #####
:: ##### stop Services so that Files aren't in use:
:stopServiceIfExists
%DBe% %0 %*
sc query %1 2>&1 >NUL
if "%ERRORLEVEL%"=="1060" GOTO :ServiceDoesntExist
net stop %1
:ServiceDoesntExist
goto :eof

:: #####
:: ##### copy all files to bin directory
:copyFileSToInstallDir
%DBe% %0
%xcp% bin "%COMT_INSTALL_PATH%\bin\
%xcp% cert "%COMT_INSTALL_PATH%\cert\
%xcp% doc "%COMT_INSTALL_PATH%\doc\
%xcp% key "%COMT_INSTALL_PATH%\key\
IF NOT EXIST "%initialDir%\key042" GOTO :LicKeyNotExist
echo copying license Key: "%initialDir%\key042"
%xcp% "%initialDir%\key042" "%COMT_INSTALL_PATH%\key\

```

```

:LicKeyNotExist
goto :eof

:: #####
:: ##### register comtarsia credential provider
:registerCredProv
%DBe% %0
reg add "HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Providers\{EE234E82-AC01-4e9f-9174-E19375BED421}" /ve /t REG_SZ /d
"ComtCredentialProvider" %regparam%
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}" /ve /t REG_SZ /d
"ComtCredentialProvider" %regparam%
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}\InprocServer32" /ve /t
REG_SZ /d "%COMT_INSTALL_PATH%\bin\ComtCredentialProvider.dll" %regparam%
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}\InprocServer32" /v
"ThreadingModel" /t REG_SZ /d "Apartment" %regparam%
goto :eof

:: #####
:: ##### apply Settings
:applySettingsAndUserInit
%DBe% %0

:: ## applydefault Regsettings
call :setPathAndVersions
%DBe% applying Defaults
"%initialDir%\%SOSInstallerDir%\%MCInstallerDir%\bin\ComtMC.exe"
"%initialDir%\%SOSInstallerDir%\%MCInstallerDir%\bin\ComtMC.exe" applydefault

:: ## remove entries that have to come from %regfile%
reg delete "HKLM\SOFTWARE\Comtarsia\SOSProfile 001\LDAP\Servers" %regparam%
reg delete "HKLM\SOFTWARE\Comtarsia\SOSProfile 001\Variables" %regparam%

call :installUserInit

REM REG IMPORT "%regfile%" %regparam%
REG IMPORT "%regfile%"
:: ## overwrite install path and versions to maks sure they're correct
call :setPathAndVersions

goto :eof

:: #####
:: ##### set install path and installed versions
:setPathAndVersions
%DBe% %0
reg add "HKLM\SOFTWARE\Comtarsia\SignOn Solutions 2008" /v "Path" /t REG_SZ /d
"%COMT_INSTALL_PATH%" %regparam%
reg add "HKLM\SOFTWARE\Comtarsia\SignOn Solutions 2008\Components" /v "Comtarsia
SignOn Solutions 2008" /t REG_SZ /d "%SOSVersion%" %regparam%
reg add "HKLM\SOFTWARE\Comtarsia\SignOn Solutions 2008\Components" /v "Comtarsia
Logon Client 2008" /t REG_SZ /d "%LCVersion%" %regparam%
goto :eof

:: #####
:: ##### copies winlogon userinit to comtarsia reg-settings and registers
comtarsia userinit as winlogon userinit
:: ##### zieht HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile
001\LogonClient userinit VOR HKLM\SOFTWARE\Comtarsia\SignOn Solutions
2008\LogonClient ??????
:installUserInit
%DBe% %0
:: ## copy winlogon userinit to comtarsia key
set ComtUserInitKey=HKEY_LOCAL_MACHINE\SOFTWARE\Comtarsia\SOSProfile
001\LogonClient

```

```

set ComtUserInitPath=%COMT_INSTALL_PATH%\bin\comtuserinit.exe

FOR /F "skip=2 tokens=2*" %%i IN ('reg query "%ComtUserInitKey%" /V "userinit"') do
set "COMT_USERINIT=%%j"
:: ## if comtUserInit is already set, assume LC has been installed already
IF "%SYSTEMROOT%\system32\userinit.exe,"=="%COMT_USERINIT%" goto
:userinitAlreadySet
set COMT_USERINIT=

FOR /F "skip=2 tokens=2*" %%i IN ('reg query "HKLM\Software\Microsoft\Windows
NT\CurrentVersion\Winlogon" /V "userinit"') do set "COMT_USERINIT=%%j"
:: ## if Winlogon Userinit is already set to "%ComtUserInitPath%", assume LC has
been installed already
IF "%ComtUserInitPath%"=="%COMT_USERINIT%" goto :userinitAlreadySet
set COMT_USERINIT=

:: ## retrieve original winlogon userinit and set it as "userinit" for LC
FOR /F "skip=2 tokens=2*" %%i IN ('reg query "HKLM\Software\Microsoft\Windows
NT\CurrentVersion\Winlogon" /V "userinit"') do set "COMT_USERINIT=%%j"
reg add "%ComtUserInitKey%" /v "userinit" /t REG_SZ /d %COMT_USERINIT% %regparam%
set COMT_USERINIT=

:: ## register Comtarsia Userinit as winlogon userinit (required for SSO and
Scripts)
reg add "HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /v "Userinit"
/t REG_SZ /d "%ComtUserInitPath%" %regparam%

GOTO :setUserInit

:userinitAlreadySet
%DBE% userinit was already set
:setUserInit
goto :eof

:: #####
:: ##### Install and start services
:installAndStartServices
%DBE% %0
:: ## install ComtRPC Service
sc create ComtRPCSrv binpath= "%COMT_INSTALL_PATH%\bin\ComtRPCSrv.exe" displayname=
"Comtarsia RPC Service"

:: ## install ComtEvent Service
"%COMT_INSTALL_PATH%\bin\ComtEventSrv.exe" -Service

:: ## start services
sc start ComtRPCSrv
sc start ComtEventSrv
goto :eof

:ERROR
echo ERROR: %ERRORSTR%
:END
cd %initialDir%

echo END
ENDLOCAL
pause

```

9.2 Customisation of the (Un-)Installation-Scripts

The file [install.cmd](#) has to be customized and copied into the directory "SOS2008-5.0.x.4".

The following lines have to be changed:

The installation directory has to be set (it has to be the same as the one that was used for the initial installation):

```
set COMT_INSTALL_PATH=C:\Program Files\Comtarsia\SignOn Solutions 2008
```

The installation path of the ComtMSSO module needs to be customized (optional):

```
set COMT_INSTALL_PATH_MSSO=C:\Program Files\Comtarsia\ComtMSSO\

REM ##### copy all files to bin directory
xcopy bin "%COMT_INSTALL_PATH%\bin\
xcopy cert "%COMT_INSTALL_PATH%\cert\
xcopy doc "%COMT_INSTALL_PATH%\doc\
xcopy key "%COMT_INSTALL_PATH%\key\
mkdir "%COMT_INSTALL_PATH%\log"

REM ##### register comtarsia credential provider

reg add
"HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Providers\{EE234E82-AC01-4e9f-9174-E19375BED421}" /ve /t REG_SZ /d
"ComtCredentialProvider" /f
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}" /ve /t REG_SZ
/d "ComtCredentialProvider" /f
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}\InprocServer32"
/ve /t REG_SZ /d "%COMT_INSTALL_PATH%\bin\ComtCredentialProvider.dll" /f
reg add "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}\InprocServer32"
/v "ThreadingModel" /t REG_SZ /d "Apartment" /f
reg add
"HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Provider Filters\{EE234E82-AC01-4e9f-9174-E19375BED421}" /ve /t REG_SZ /d
"ComtCredentialProvider" /f

REM ##### create SOSProfile key
reg add "HKLM\SOFTWARE\Comtarsia\SOSProfile 001" /v "Path" /t REG_SZ /d
"%COMT_INSTALL_PATH%" /f

REM ##### applydefault Regsettings
bin\ComtMC applydefault

REM ##### copy winlogon userinit to comtarsia key
FOR /F "skip=2 tokens=2*" %%i IN ('reg query
"HKLM\SOFTWARE\Comtarsia\SOSProfile 001\LogonClient" /V "userinit"') do set
"COMT_USERINIT=%%j"
if NOT "%SYSTEMROOT%\system32\userinit.exe"=="%COMT_USERINIT%" goto
install_services
set COMT_USERINIT=
FOR /F "skip=2 tokens=2*" %%i IN ('reg query
"HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /V "userinit"')
do set "COMT_USERINIT=%%j"
if "%COMT_INSTALL_PATH%\bin\comtuserinit.exe"=="%COMT_USERINIT%" goto
install_services
```

```

FOR /F "skip=2 tokens=2*" %%i IN ('reg query
"HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /v "userinit")
do set "COMT_USERINIT=%~j"
reg add "HKLM\SOFTWARE\COMTARSIA\SOSProfile 001\LogonClient" /v "Userinit"
/t REG_SZ /d %COMT_USERINIT% /f
set COMT_USERINIT=

reg add "HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /v
"Userinit" /t REG_SZ /d "%COMT_INSTALL_PATH%\bin\comtuserinit.exe" /f

:install_services
reg import my-SOSProfile001.reg

REM ##### install ComtRPC Service
sc create ComtRPCSrv binpath= "%COMT_INSTALL_PATH%\bin\ComtRPCSrv.exe"
displayname= "Comtarsia RPC Service"

REM ##### install ComtEvent Service
"%COMT_INSTALL_PATH%\bin\ComtEventSrv.exe" -Service

REM ##### start ComtRPC Service
sc start ComtRPCSrv

REM ##### start ComtEvent Service
sc start ComtEventSrv

Installation of the ComtMSSO module (optional. Comment out if unused)
REM ###### ComtMSSO
vs_piaredist.exe /q
xcopy ComtMSSO "%COMT_INSTALL_PATH_MSSO%" /s /e /y

A custom logon tile bitmap has to be specified (optional):
REM ###### PanelBitmap
xcopy myPanelBitmap.bmp "%COMT_INSTALL_PATH%\bin\"
```

The file [uninstall.cmd](#) has to be customized and copied to the directory "SOS2008-5.0.x.4".

The installation directory has to be set (it has to be the same as the one that was used for the initial installation):

```

set COMT_INSTALL_PATH=C:\Program Files\Comtarsia\SignOn Solutions 2008
set COMT_INSTALL2=C:\Program Files\Comtarsia

REM ##### copy winlogon userinit to comtarsia key
FOR /F "skip=2 tokens=2*" %%i IN ('reg query
"HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /v "userinit")
do set "COMT_USERINIT=%~j"
if NOT "%COMT_INSTALL_PATH%\bin\comtuserinit.exe"=="%COMT_USERINIT%" goto
uninstall_services

FOR /F "skip=2 tokens=2*" %%i IN ('reg query
"HKLM\SOFTWARE\Comtarsia\SOSProfile 001\LogonClient" /v "userinit") do set
"COMT_USERINIT=%~j"
reg add "HKLM\Software\Microsoft\Windows NT\CurrentVersion\Winlogon" /v
"Userinit" /t REG_SZ /d "%COMT_USERINIT%" /f
set COMT_USERINIT=

:uninstall_services

REM ##### start ComtRPC Service
sc stop ComtRPCSrv

REM ##### start ComtEvent Service
```

```
sc stop ComtEventSrv

REM ##### install ComtRPC Service
sc delete ComtRPCSrv

REM ##### install ComtEvent Service
sc delete ComtEventSrv

REM ##### Unregister Comtarsia Credential Provider
reg delete "HKLM\SOFTWARE\Comtarsia"
reg delete "HKCR\CLSID\{EE234E82-AC01-4e9f-9174-E19375BED421}"
reg delete
"HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Providers\{EE234E82-AC01-4e9f-9174-E19375BED421}"

REM ##### Register Microsoft Credential Provider
reg add
"HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Providers\{6f45dc1e-5384-457a-bc13-2cd81b0d28ed}" /ve /t REG_SZ /d
>PasswordProvider" /f
reg add
"HKLM\SOFTWARE\Microsoft\Windows\CurrentVersion\Authentication\Credential
Providers\{6f45dc1e-5384-457a-bc13-2cd81b0d28ed}\LogonPasswordReset" /ve /t
REG_SZ /d "{8841d728-1a76-4682-bb6f-a9ea53b4b3ba}" /f

rmdir /S /Q "%COMT_INSTALL_PATH2%"
```

10. Disclaimer

All pages are subject to copyright and may only be copied or integrated in own offers with the written permission of Comtarsia IT Services.

All Rights reserved.

Subject to changes without notice!

Comtarsia IT Services does not give any assurance or guarantee for other websites, to which we refer in this manual. If you access a non-Comtarsia IT Services Website, it is an independent site beyond our control.

This is also valid, if this site contains the Comtarsia IT Services logo.

In addition, a link from our site to another does not mean that we identify ourselves with their content or support their use.